





the Elsie K Baglet

Step 40-42 — Attaching Floor 1 to Wide Panel



40) Move both zipper pulls to center of zipper then sandwich one set of Wide Panel end edges between end edges of Floor 1 (#18) in contrast & lining aligning end edges RST. Stitch in place a FULL 1/4" from edges.



41) Now sandwich the remaining Wide Panel end edges between RS's of remaining end edges of Floor 1 in contrast & lining. Stitch in place a FULL 1/4" from edges.

FYI— I included both of these pictures since it's a bit of an awkward attachment. I thought seeing both of them would be helpful.



41 cont.) Trim both zipper ends even w/fabric edges then flip entire unit RSO. Press all seams away toward Floor 1. Topstitch close to both seams



42) Align ALL long outside lining & contrast edges. Stitch them in place a scant 1/4" from edges around entire circumference of unit to secure them. Set Wide Panel unit aside for step 51.

Here's how your Wide Panel should look when its completed.